



Outlook 2007 Setup


Open Outlook 2007 and go to Tools -> Account Settings.



Make Sure you are on the E-mail tab and click “New.”



Select “Microsoft Exchange, POP3, IMAP, or HTTP” and click Next.



On the following page do not enter any information. Check “Manually configure server settings or additional server types” and click Next.

Add New E-mail Account

Auto Account Setup

Your Name:
Example: Barbara Sankovic

E-mail Address:
Example: barbara@contoso.com

Password:
ReType Password:
Type the password your Internet service provider has given you.

Manually configure server settings or additional server types

< Back Next > Cancel

Select “Internet E-Mail” and click Next.

Internet E-mail
Connect to your POP, IMAP, or HTTP server to send and receive e-mail messages.

Microsoft Exchange
Connect to Microsoft Exchange for access to your e-mail, calendar, contacts, faxes and voice mail.

Other
Connect to a server type shown below.

Fax Mail Transport
Outlook Mobile Service (Text Messaging)

Enter the following information.

Your Name: Enter your name as you want it to appear on outgoing messages.

E-mail Address: Your email address.

Account type: Select “IMAP.”

Incoming mail server: imap.mailanyone.net

Outgoing mail server (SMTP): smtp.mailanyone.net

Click on “More Settings.”

Add New E-mail Account

Internet E-mail Settings
Each of these settings are required to get your e-mail account working.

User Information
Your Name: John Smith
E-mail Address: johnsmith@wizmail.com

Server Information
Account Type: IMAP
Incoming mail server: imap.mailanyone.net
Outgoing mail server (SMTP): smtp.mailanyone.net

Logon Information
User Name: johnsmith
Password: *****
 Remember password
 Require logon using Secure Password Authentication (SPA)

Test Account Settings
After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)
Test Account Settings ...

More Settings ...

< Back Next > Cancel

Click on the Outgoing Server tab.

Check "My outgoing server requires authentication."

Internet E-mail Settings


General Folders **Outgoing Server** Connection Advanced

My outgoing server (SMTP) requires authentication
 Use same settings as my incoming mail server
 Log on using
User Name: _____
Password: _____
 Remember password
 Require Secure Password Authentication (SPA)


OK Cancel

Click on the Advanced Tab. Where it says Outgoing server (SMTP): 25, change this to 2500.

Where it says "Root folder path," enter "INBOX" (without quotes).



Click on the Folders tab. Select the second radio button (“Choose an existing folder...”). Expand the tree and select your WizMailer Sent Items folder.



Click Next.

Click Finish to complete the setup.